



SECURE-TSPLOYER
SECURE FLASH MP3 PLAYER

skin installation





SECURE-TSPloyer is an mp3 audio player. Amongst the multiple features and functionalities SECURE-TSPloyer offers, there is the utility that enables the user to change the skin shown with the audio player, so it matches the web design where it is inserted. This is why Trio Solutions has developed a group of skins for a wide variety of clients, while it also provides a design and implementation service of these skins for clients wishing to show an exclusive web environment that fits and blends completely with their web design.





STEPS TO FOLLOW IN ORDER TO CHANGE YOUR PLAYER'S SKIN

1. Download the compressed (.zip) file of the skin of your choice.
This file should contain a) a file with the .swf extension, with the name matching the desired skin, b) a readme.txt file, which will contain the license for the skin and c) a .pdf file that serves as the user's manual.
2. Unzip the file you downloaded to a folder of your choice (ex. c:/Temp).
3. Copy the .swf file to the folder on your web server, where the rest of the skins are stored. (ex. SECURE-TSPlayer/skin)

Once the environment file has been copied into the appropriate folder on the web server, a change in the configuration.xml file is required so that the audio player can show the new skin.

4. Open the setup file, configuration.xml, in editing mode (for this purpose you can use Adobe Dreamweaver or any other text editor) and introduce the URL address where the new skin is found. The configuration.xml file contains a set of options to setup the audio player.

The file structure is as follows:


```
<?xml version="1.0" encoding="iso-8859-1"?>
<tsplayer>
  <skinoptions>
    <skin>../skin/ts1.swf</skin>
    <playlist>1</playlist>
  </skinoptions>
  <functionality>
    <streaming>1</streaming>
    <autoplay>1</autoplay>
    <volume>100</volume>
    <repeat>0</repeat>
    <shuffling>1</shuffling>
  </functionality>
</tsplayer>
```

where:

`<skin></skin>` contains the URL address of the skin that will be displayed by the player, this URL address can be absolute, within the same domain in which that the player is located (ex. <http://www.mywebaddress.com/SECURE-TSPlayer/skin/skinname.swf>), or it can be relative to the webpage where the audio player is inserted (ex. `SECURE-TSPlayer/skin/skinname.swf`, in case the directory SECURE-TSPlayer is located at the same level as the webpage where the audio player is inserted).

SECURE-TSPlayer as an extension for Adobe Dreamweaver

If you acquired SECURE-TSPlayer as an extension for Adobe Dreamweaver, when inserting the audio player in the webpage, you can choose the skin of your liking from the “select skin” option of the setup screen.



ClassicSECURE-TSPlayerV4.5

Select Skin for SECURE-TSPlayer

Player Configuration Options

Secure Player

Insert Password

Play in Streaming

Initial Volume Value (0..100)

Show Playlist

Autoplay

Active Repeat Play List Button

Active Shuffling Selection Button

Initial configuration of the SECURE-TSPlayer audio player when it is loaded into the webpage.